
The Metadata in TIFF files

The Tagged Image File Format is a container. It's very flexible and can deal with multiple pages, different colour spaces and frame configurations, as well as metadata. The specification is available from: https://partners.adobe.com/public/developer/en/tiff/TIFF6.pdf

The TIFF container is so flexible it is used as the structure for most RAW formats including Adobe's DNG. Additionally the TIFF container is used to store the metadata that lies inside the Exif blocks embedded in JPEG and PNG files.

There is a 64bit version of Tiff called **BigTiff**. This is currently not supported by exiv2.



The format consists of an 8 byte header which provides a 2 byte endian flag (II or MM), a 2 byte type "magic number" (42) and a 4 byte offset to an *Image File Directory*.

The **IFD** (Image File Directory) has a two byte header which contains the length of the directory followed by 12 byte "fields" or "tags". The trailing 4 bytes of the directory is the offset to the next directory **or** zero to terminate the directory chain.

A tag consists of a 12 byte record: TagID, TagType, Count and Offset which are 2,2,4 and 4 bytes respectively. The TagID defines the purpose of the record (Width, Height, ColorSpace etc) and the TagType defines the data format. Count and Offset are used to contain the raw data *or* provide an offset in the file at which to read the raw data for this tag.

Example:

The version of exiv2(.exe) which ships with v0.25 provides options -pS to reveals the structure of the TIFF and option -pX is used to extract the raw XMP/xml data.

The option -pv is used to print the metadata values.

x00fe Image	NewSubfileType	Long	1	0
x0100 Image	ImageWidth	Short	1	282
x0101 Image	ImageLength	Short	1	212
x0102 Image	BitsPerSample	Short	3	8 8 8
x0103 Image	Compression	Short	1	5
x0106 Image	PhotometricInterpretation	Short	1	2
x010e Image	ImageDescription	Ascii	32	
x010f Image	Make	Ascii	5	SONY
x0110 Image	Model	Ascii	9	DSC-S600
x0111 Image	StripOffsets	Long	16	4372 14864
x0112 Image	Orientation	Short	1	1
x0115 Image	SamplesPerPixel	Short	1	3
x0116 Image	RowsPerStrip	Long	1	14
x0117 Image	StripByteCounts	Long	16	10492
x011a Image	XResolution	Rational	1	96/1
x011b Image	YResolution	Rational	1	96/1
x011c Image	PlanarConfiguration	Short	1	1
x0128 Image	ResolutionUnit	Short	1	2
x0132 Image	DateTime	Ascii	20	2009:04:26 12:38:18
x013d Image	Predictor	Short	1	1
x0153 Image	SampleFormat	Short	3	1 1 1
x02bc Image	XMLPacket	Byte	2505	(Binary value suppressed)
x8773 Image	InterColorProfile	Undefined	1352	(Binary value suppressed)

```
$ exiv2 -pS test/data/test.tiff
STRUCTURE OF TIFF FILE (II): test/data/test.tiff
address
                                                    type
                                                              count |
                                                                         offset
                                                                                   value
              tag
           0x00fe NewSubfileType
      10
                                                    LONG
                                                                  1
                                                                              0
                                                                                   0
           0x0100 ImageWidth
                                                   SHORT
                                                                  1
                                                                             282
                                                                                   282
      22
                                                   SHORT
      34
           0x0101 ImageLength
                                                                  1
                                                                             212
                                                                                   212
      46
           0x0102 BitsPerSample
                                                   SHORT
                                                                  3
                                                                             290
                                                                                   8 8 8
      58
          0x0103 Compression
                                                   SHORT
                                                                  1
                                                                              5
                                                                                   5
          0x0106 PhotometricInterpretation
                                                   SHORT
      70
                                                                  1
                                                                              2
                                                                                   2
      82
          0x010e ImageDescription
                                                   ASCII
                                                                 32
                                                                             296
      94
           0x010f Make
                                                   ASCII
                                                                  5
                                                                             328
                                                                                   SONY
     106
           0x0110 Model
                                                   ASCII
                                                                  9
                                                                                   DSC-S600
                                                                             334
          0x0111 StripOffsets
     118
                                                    LONG
                                                                 16
                                                                             344
                                                                                   4372 14864 25634 37110 50496 ...
     130
          0x0112 Orientation
                                                   SHORT
                                                                  1
                                                                              1
                                                                                   1
     142
           0x0115 SamplesPerPixel
                                                   SHORT
                                                                  1
                                                                              3
                                                                                   3
          0x0116 RowsPerStrip
                                                    LONG
     154
                                                                  1
                                                                             14
                                                                                  14
     166
          0x0117 StripByteCounts
                                                    LONG
                                                                 16
                                                                             408
                                                                                   10492 10770 11476 13385 13348 ...
     178
          0x011a XResolution
                                                RATIONAL
                                                                  1
                                                                             472
                                                                                   96/1
     190
          0x011b YResolution
                                                RATIONAL
                                                                  1
                                                                             480
                                                                                   96/1
          0x011c PlanarConfiguration
                                                   SHORT
     202
                                                                  1
                                                                              1
                                                                                   1
     214
          0x0128 ResolutionUnit
                                                   SHORT
                                                                  1
                                                                              2
                                                                                   2
          0x0132 DateTime
                                                                 20
                                                                                   2009:04:26 12:38:18
                                                   ASCII
                                                                             488
          0x013d Predictor
                                                   SHORT
     238
                                                                  1
                                                                              1
                                                                                   1
     250 l
          0x0153 SampleFormat
                                                   SHORT
                                                                  3
                                                                             508
                                                                                  1 1 1
                                                                                   <?xpacket begin="..." id="W5M0Mp ...</pre>
     262
          0x02bc XMLPacket
                                                    BYTE
                                                               2505
                                                                             514
     274 | 0x8773 InterColorProfile
                                              UNDEFINED
                                                               1352
                                                                            3020 | ...Happl. ..scnrRGB XYZ .......
FND test/data/test.tiff
$ exiv2 -pX test/data/test.tiff | xmllint --format -
<?xml version="1.0"?>
<?xpacket begin="" id="W5M0MpCehiHzreSzNTczkc9d"?>
<x:xmpmeta xmlns:x="adobe:ns:meta/" x:xmptk="XMP Core 4.4.0-Exiv2">
  <rdf:RDF xmlns:rdf="http://www.w3.org/1999/02/22-rdf-syntax-ns#">
   <rdf:Description xmlns:dc="http://purl.org/dc/elements/1.1/" rdf:about="">
      <dc:title>
        <rdf:Alt>
          <rdf:li xml:lang="x-default">this is a test image</rdf:li>
        </rdf:Alt>
      </dc:title>
    </rdf:Description>
  </rdf:RDF>
</x:xmpmeta>
<?xpacket end="w"?>
```

You can use the output from -ps to determine the location of the XMLPacket:

```
$ exiv2 -pS test/data/test.tiff | grep XMLPacket 262 | 0x02bc XMLPacket | BYTE | 2505 | 514 | <?xpacket begin="..." id="W5M0Mp ... $
```

You can see the XMLPacket of 2505 bytes stored at offset 514. You can extract the XMP with the following command:

```
$ dd bs=1 count=2505 skip=514 if=test/data/test.tiff | xmllint --format -
2505+0 records in
2505+0 records out
2505 bytes (2.5 kB) copied, 0.0064 s, 391 kB/s
<?xml version="1.0"?>
<?xpacket begin="" id="W5M0MpCehiHzreSzNTczkc9d"?>
<x:xmpmeta xmlns:x="adobe:ns:meta/" x:xmptk="XMP Core 4.4.0-Exiv2">
  <rdf:RDF xmlns:rdf="http://www.w3.org/1999/02/22-rdf-syntax-ns#">
   <rdf:Description xmlns:dc="http://purl.org/dc/elements/1.1/" rdf:about="">
      <dc:title>
        <rdf:Alt>
         <rdf:li xml:lang="x-default">this is a test image</rdf:li>
        </rdf:Alt>
      </dc:title>
   </rdf:Description>
  </rdf:RDF>
</x:xmpmeta>
<?xpacket end="w"?>
```

The option -pX doesn't use dd to achieve the same result and is much more convenient to use.

To demonstrate that the metadata block in a JPEG is a TIFF file, extract and print the structure.

```
8762
           0xffe1 APP1
                             5329
                                    http://ns.adobe.com/xap/1.0/.<?x
           0xffe2 APP2
                                    ICC_PROFILE.....0ADBE....mntrRG chunk 1/1
   14093
                              576
   14671
           0xffee APP14
                               14
                                    Adobe.d@.....
   14687
           0xffdb DOT
                              132
           0xffc0 SOF0
                               17
   14821
   14840
           0xffdd DRI
                                4
   14846
           0xffc4 DHT
                              418
   15266
          0xffda SOS
$
```

We can extract the APP1/Exif data as follows:

```
$ dd bs=1 skip=$((2+2+8)) count=$((5718-8)) if=test/data/Reagan.jpg of=ReaganExif.tiff
5710+0 records in
5710+0 records out
5710 bytes (5.7 kB) copied, 0.026688 s, 214 kB/s
$ exiv2 -pS ReaganExif.tif
STRUCTURE OF TIFF FILE (MM): ReaganExif.tif
address
              tag
                                                     type
                                                                count
                                                                           offset
                                                                                    value
           0x0100 ImageWidth
                                                                         13107200
      10
                                                    SHORT
                                                                   1
                                                                                    200
                                                    SHORT
                                                                          8519680
      22
           0x0101 ImageLength
                                                                   1
                                                                                    130
      34
           0x0102 BitsPerSample
                                                    SHORT
                                                                   4
                                                                              242
                                                                                    8 8 8 8
      46
           0x0103 Compression
                                                    SHORT
                                                                   1
                                                                            65536
                                                                                    1
      58
           0x0106 PhotometricInterpretation
                                                    SHORT
                                                                    1
                                                                           131072
      70
           0x010e ImageDescription
                                                    ASCII
                                                                  403
                                                                                    040621-N-6536T-062.USS Ronald Re ...
                                                                              250
      82
           0x010f Make
                                                    ASCII
                                                                  18
                                                                              653
                                                                                    NIKON CORPORATION
      94
           0x0110 Model
                                                    ASCII
                                                                   10
                                                                                    NIKON D1X
                                                                              671
     106
           0x0112 Orientation
                                                    SHORT
                                                                   1
                                                                            65536
                                                                                    1
           0x0115 SamplesPerPixel
     118
                                                    SHORT
                                                                   1
                                                                           262144
                                                                                    4
     130
           0x011a XResolution
                                                 RATIONAL
                                                                   1
                                                                              681
                                                                                    3000000/10000
     142
           0x011b YResolution
                                                 RATIONAL
                                                                   1
                                                                              689
                                                                                     3000000/10000
           0x011c PlanarConfiguration
                                                    SHORT
     154
                                                                   1
                                                                            65536
                                                                                    1
           0x0128 ResolutionUnit
     166
                                                    SHORT
                                                                   1
                                                                           131072
     178
           0x0131 Software
                                                    ASCII
                                                                   40
                                                                              697
                                                                                    Adobe Photoshop Elements 12.0 Ma ...
           0x0132 DateTime
     190
                                                    ASCII
                                                                   20
                                                                              737
                                                                                    2016:09:13 11:58:16
     202
           0x013h Artist
                                                    ASCII
                                                                   34
                                                                              757
                                                                                    Photographer..s Mate 3rd Class ( ...
     214
           0x8769 ExifTag
                                                     LONG
                                                                   1
                                                                              792
                                                                                    792
           0x8825 GPSTag
                                                     LONG
                                                                   1
                                                                             1400
     226
                                                                                    1400
    1422
           0x0103 Compression
                                                    SHORT
                                                                   1
                                                                           393216
                                                                                    6
           0x011a XResolution
                                                 RATTONAL
                                                                                    72/1
    1434
                                                                   1
                                                                             1498
    1446
           0x011b YResolution
                                                 RATIONAL
                                                                   1
                                                                             1506
                                                                                    72/1
    1458
           0x0128 ResolutionUnit
                                                    SHORT
                                                                    1
                                                                           131072
                                                                                    2
    1470
           0x0201 JPEGInterchangeFormat
                                                     LONG
                                                                   1
                                                                             1514
                                                                                    1514
                                                                   1
    1482 | 0x0202 JPEGInterchangeFormatLeng |
                                                     LONG |
                                                                             4196 l
                                                                                    4196
END ReaganExif.tif
```

The version of the exiv2 utility that ships with v0.26 later has an option -pR which Recursively prints the structure of an image file. Recursively means the utility prints structures embedded within other structures. For example, the Exif metadata in a JPEG is encoded as a TIFF embedded in the APP1/Exif segment of the JPEG.

```
$ exiv2 -pR test/data/Reagan.jpg
STRUCTURE OF JPEG FILE: test/data/Reagan.jpg
address | marker
                        | length | data
          0xffd8 SOT
      0
       2 | 0xffe1 APP1 |
                             5718 | Exif..MM.*.....
  STRUCTURE OF TIFF FILE (MM): MemIo
   address
                                                                count
                                                                           offset
                                                                                    value
                tag
                                                      tvpe
        10
             0x0100 ImageWidth
                                                     SHORT
                                                                    1
                                                                         13107200
                                                                                    200
                                                     SHORT
        22
             0x0101 ImageLength
                                                                    1
                                                                          8519680
                                                                                    130
        34
             0x0102 BitsPerSample
                                                     SHORT
                                                                    4
                                                                              242
                                                                                    8 8 8 8
        46
             0x0103 Compression
                                                     SHORT
                                                                    1
                                                                            65536
                                                                                    1
        58
             0x0106 PhotometricInterpretation
                                                     SHORT
                                                                    1
                                                                           131072
                                                                                    040621-N-6536T-062.USS Ronald Re ...
        70
             0x010e ImageDescription
                                                     ASCII
                                                                  403
                                                                              250
             0x010f Make
                                                                                    NIKON CORPORATION
        82
                                                     ASCII
                                                                   18
                                                                              653
        94
             0x0110 Model
                                                     ASCII
                                                                   10
                                                                              671
                                                                                    NIKON D1X
       106
             0x0112 Orientation
                                                     SHORT
                                                                            65536
                                                                    1
                                                                                    1
       118
             0x0115 SamplesPerPixel
                                                     SHORT
                                                                    1
                                                                           262144
       130
             0x011a XResolution
                                                  RATIONAL
                                                                    1
                                                                              681
                                                                                    681/0
       142
             0x011b YResolution
                                                  RATIONAL
                                                                    1
                                                                              689
                                                                                    689/0
             0x011c PlanarConfiguration
       154
                                                     SHORT
                                                                    1
                                                                            65536
                                                                                    1
             0x0128 ResolutionUnit
                                                     SHORT
                                                                    1
                                                                           131072
       166
            0x0131 Software
                                                                   40
                                                                              697
                                                                                    Adobe Photoshop Elements 12.0 Ma ...
       178
                                                     ASCII
       190
             0x0132 DateTime
                                                     ASCII
                                                                   20
                                                                              737
                                                                                     2016:09:13 11:58:16
       202
             0x013b Artist
                                                     ASCII
                                                                   34
                                                                              757
                                                                                     Photographer..s Mate 3rd Class ( ...
            0x8769 ExifTag
                                                                              792
                                                                                    792
       214
                                                     LONG
                                                                    1 |
   STRUCTURE OF TIFF FILE (MM): MemIo
     address
                                                                             offset
                  tag
                                                        tvpe
                                                                  count
                                                                                      value
         794
               0x829a ExposureTime
                                                    RATIONAL
                                                                      1
                                                                               1254
                                                                                      1254/0
         806
                                                    RATTONAL
                                                                      1
                                                                               1262
                                                                                      1262/0
               0x829d FNumber
         818
               0x8822 ExposureProgram
                                                       SHORT
                                                                      1
                                                                              65536
                                                                                      1
              0x9000 ExifVersion
                                                                          808596016 | 0220
                                                   UNDEFINED
```

```
0x9003 DateTimeOriginal
                                                      ASCII
                                                                      20
                                                                                1270
                                                                                       2004:06:21 23:37:53
       842
             0x9004 DateTimeDigitized
                                                                     20
       854
                                                      ASCII
                                                                                1290
                                                                                       2004:06:21 23:37:53
       866
             0x9101 ComponentsConfiguration
                                                  UNDEFINED
                                                                      4
                                                                            16909056
             0x9102 CompressedBitsPerPixel
                                                   RATIONAL
       878
                                                                      1
                                                                                1310
                                                                                       1310/0
             0x9201 ShutterSpeedValue
                                                  SRATIONAL
                                                                                       1318/0
       890
                                                                      1
                                                                                1318
       902
             0x9202 ApertureValue
                                                   RATTONAL
                                                                      1
                                                                                1326
                                                                                       1326/0
       914
             0x9204 ExposureBiasValue
                                                  SRATIONAL
                                                                      1
                                                                                1334
                                                                                       1334/0
       926
             0x9205 MaxApertureValue
                                                   RATIONAL
                                                                      1
                                                                                1342
                                                                                       1342/0
       938
             0x9207 MeteringMode
                                                       SHORT
                                                                      1
                                                                              131072
                                                                                       2
       950
             0x9208 LightSource
                                                       SHORT
                                                                      1
                                                                              655360
                                                                                       10
       962
             0x9209 Flash
                                                       SHORT
                                                                      1
       974
             0x920a FocalLength
                                                   RATIONAL
                                                                                1350
                                                                      1
                                                                                       1350/0
                                                                          808845312
       986
             0x9290 SubSecTime
                                                      ASCII
                                                                      3
                                                                                       96
       998
             0x9291 SubSecTimeOriginal
                                                       ASCII
                                                                      3
                                                                           808845312
                                                                                       06
      1010
             0x9292 SubSecTimeDigitized
                                                       ASCII
                                                                      3
                                                                           808845312
                                                                                       06
             0xa000 FlashpixVersion
                                                  UNDEFINED
                                                                      4
                                                                          808529968
                                                                                       0100
      1022
      1034
             0xa001 ColorSpace
                                                       SHORT
                                                                      1
                                                                          4294901760
                                                                                       65535
      1046
             0xa002 PixelXDimension
                                                        LONG
                                                                      1
                                                                                 200
                                                                                       200
      1058
             0xa003 PixelYDimension
                                                       LONG
                                                                      1
                                                                                 130
                                                                                       130
                                                       SHORT
      1070
             0xa217 SensingMethod
                                                                      1
                                                                             131072
                                                                                       2
      1082
             0xa300 FileSource
                                                  UNDEFINED
                                                                      1
                                                                            50331648
             0xa301 SceneType
                                                  UNDEFINED
      1094
                                                                      1
                                                                            16777216
                                                       SHORT
                                                                                       0
      1106
             0xa401 CustomRendered
                                                                      1
                                                                                   0
                                                                               65536
      1118
             0xa402 ExposureMode
                                                       SHORT
                                                                      1
                                                                                       1
      1130
             0xa403 WhiteBalance
                                                       SHORT
                                                                      1
                                                                               65536
      1142
             0xa404 DigitalZoomRatio
                                                   RATIONAL
                                                                      1
                                                                                1358
                                                                                       1358/0
             0xa405 FocalLengthIn35mmFilm
      1154
                                                       SHORT
                                                                      1
                                                                             4128768
                                                                                       63
      1166
             0xa406 SceneCaptureType
                                                       SHORT
                                                                      1
                                                                                   0
                                                                                       0
      1178
             0xa407 GainControl
                                                       SHORT
                                                                      1
                                                                                   0
                                                                                       0
      1190
             0xa408 Contrast
                                                       SHORT
                                                                      1
                                                                                   0
                                                                                       0
      1202
             0xa409 Saturation
                                                       SHORT
                                                                                   0
                                                                                       0
                                                                      1
      1214
             0xa40a Sharpness
                                                       SHORT
                                                                      1
                                                                                   0
                                                                                       0
      1226
             0xa40c SubjectDistanceRange
                                                       SHORT
                                                                      1
                                                                                   0
      1238
             0xa420 ImageUniqueID
                                                      ASCII
                                                                     33
                                                                                1366 | 127c1377b054a3f65bf2754ebb24e7f2 ...
 END MemIo
           0x8825 GPSTag
     226
                                                     LONG
                                                                    1
                                                                              1400
                                                                                     1400
    1422
           0x0103 Compression
                                                     SHORT
                                                                    1
                                                                            393216
                                                 RATIONAL
                                                                                     1498/0
    1434
           0x011a XResolution
                                                                    1
                                                                              1498
    1446
           0x011b YResolution
                                                 RATIONAL
                                                                    1
                                                                              1506
                                                                                     1506/0
                                                    SHORT
                                                                            131072
    1458
           0x0128 ResolutionUnit
                                                                    1
    1470
           0x0201 JPEGInterchangeFormat
                                                     LONG
                                                                    1
                                                                             1514
                                                                                     1514
    1482
           0x0202 JPEGInterchangeFormatLeng |
                                                     LONG
                                                                    1 |
                                                                              4196
                                                                                     4196
END MemIo
 5722
         0xffed APP13
                            3038 | Photoshop 3.0.8BIM.....Z...
        DataSet
                   Name
Record
                                                Length |
                                                         Data
     1
              90
                   CharacterSet
                                                     3
                                                          . %G
     1
              90
                   CharacterSet
                                                     3
                                                          .%G
     2
               0
                   RecordVersion
                                                     2
                                                          040621-N-6536T-062.USS Ronald Reagan (CV...
     2
                   Caption
                                                   402
             120
     2
             122
                   Writer
                                                     9
                                                          Dir. NVNS
     2
                    SpecialInstructions
                                                          Credit as U.S. Navy photo by Elizabeth T...
                                                    49
     2
                                                          Photographer..s Mate 3rd Class (
              80
                   Bvline
                                                    32
                   BylineTitle
                                                          U.S Navy Photographer
     2
              85
                                                    21
     2
             110
                   Credit
                                                     8
                                                          U.S Navy
     2
             115
                    Source
                                                    24
                                                          Navy Visual News Service
                                                          040621-N-6536T-062
     2
                   ObjectName
                                                    18
               5
     2
              55
                   DateCreated
                                                     8
                                                          20040621
     2
                    TimeCreated
                                                    11
                                                          000000+0000
              60
     2
              62
                   DigitizationDate
                                                     8
                                                          20040621
     2
              63
                   DigitizationTime
                                                    11
                                                          233753-0400
     2
              90
                   City
                                                    19
                                                          Straits of Magellan
     2
             101
                    CountryName
                                                    13
                                                          South America
     2
              15
                   Category
                                                     1
     2
                    SuppCategory
                                                          703-614-9154
              20
                                                    12
     2
              20
                    SuppCategory
                                                    23
                                                          navyvisualnews@navy.mil
     2
              20
                    SuppCategory
                                                    11
                                                          UNCLASSFIED
     2
              10
                   Urgency
                                                     1
                                                          5
     2
              25
                   Keywords
                                                    13
                                                          ronald reagan
     2
              25
                    Keywords
                                                     6
                                                          reagan
     2
              25
                    Keywords
                                                     6
                                                          cvn 76
                   Keywords
                                                          cvn-76
     2
              25
                                                     6
     2
              25
                    Keywords
                                                    18
                                                          straights magellan
     2
              25
                    Keywords
                                                     8
                                                          magellan
                   Keywords
                                                     7
     2
              25
                                                          carrier
     2
              25
                   Keywords
                                                    12
                                                          nimitz-class
     2
              25
                   Keywords
                                                     4
                                                          ship
              25
                   Keywords
                                                     8 | underway
         0xffe1 APP1
                                   http://ns.adobe.com/xap/1.0/.<?x</pre>
 8762
                            5329
14093
         0xffe2 APP2
                             576
                                   ICC_PROFILE.....0ADBE....mntrRG chunk 1/1
14671
         0xffee APP14
                              14
                                 Adobe.d@.....
14687
         0xffdb DQT
                             132
         0xffc0 SOF0
                              17
14821
14840
         0xffdd DRI
                               4
         0xffc4 DHT
                             418
```

15266 | 0xffda SOS

Updated by Robin Mills about 5 years ago \cdot 20 revisions